

ECMPS 2018 Quarter 3 Release Notes

I. Introduction

The 2018 Quarter 3 release of the ECMPS Client Tool includes new functionality for the Texas SO2 Rule as well as several bug fixes.

II. Interface/ Database Changes

A. New and Modified Functionality

- Added the ability to report data for the Texas SO2 Rule (TXSO2)

B. Bug Fixes

- Updated the display of QA certification event descriptions.
- Updated the MATS SO2 emissions screen to display the MODC from the SO2 MHV record.

III. Check Changes

A. New and Modified Checks

- Added checks to ensure that the activation date for a PGVP vendor is prior to the test date.
- Added checks to verify reported rate values for MATS parameters when a multi-stack configuration is using the MS-1 formula to calculate the rate for a unit.
- Added a check to ensure SO2 concentration is replaced with 2.0 only when the MODC for the hour is 16 and the unadjusted hourly SO2 concentration is less than 2.0ppm.

Check ID
DAYCAL 28
HOURAPP 10, 11, 12, 13
HOURMHV 16
PGVP 3

B. Bug Fixes

- Corrected check result message to clarify the type of qualification record that is missing.

- Updated checks to not fire for SO2RH or SO2RE on hours where the MODC of 16 is used for SO2C.
- Updated checks to ensure QA Cert Event Cods 100 and 101 get the appropriate amount of conditional data hours.

Check ID
HOURGEN 17
MATSCHV 20
MATSMHV 19, 20

IV. XSD Changes

A. New and Modified Functionality

- None

V. Known Issues

[Click here to view current list of Known Issues.](#)

VI. Requested Enhancements

[Click here to view the status of Requested Enhancements.](#)